# Registermap

### **LEDG**

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0	
Name	-	-	-	-	-	-	-	-	- LEDG								
Mode	r0	r0	rO	r0	r0	r0	r0	rO				\	v				
Reset	-	-	-	-	-	-	-	-				0x	00				

LED Green Register Address: 0x4000

### **LEDR**

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-					LE	DR				
Mode	r0	r0	r0	r0	r0	r0					١	v				
Reset	-	-	-	-	-	-					0x0	000				

LED Red Register Address: 0x4002

### HEX0

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-	-				HEX0			
Mode	r0				w											
Reset	-	-	-	-	-	-	-	-	-				0x7f			

Seven Segment Digit 0 Register Address: 0x4010

### HEX1

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-	-				HEX1			
Mode	rO	rO	r0	rO	rO	r0	rO	rO	rO				w			
Reset	-	-	-	-	-	-	-	-	-				0x7f			

Seven Segment Digit 1 Register

Address: 0x4012

### HEX2

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-	-	- HEX2						
Mode	r0	rO	r0	rO	rO	rO	r0	rO	r0				w			
Reset	-	-	-	-	-	-	-	-	-				0x7f			

Seven Segment Digit 2 Register

Address: 0x4014

#### HEX3

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-	-				HEX2			
Mode	r0	r0	r0	r0	rO	r0	r0	r0	r0				w			
Reset	-	-	-	-	-	-	-	-	-				0x7f			

Seven Segment Digit 3 Register

Address: 0x4016

### KEY

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-	-	-	-	-				
Mode	r0															
Reset	-	-	-	-	-	-	-	-	-	-	-	-				

Pushbuttons Register Address: 0x4020

### SW

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-					S	W				
Mode	r0	rO	r0	r0	r0	r0					ı	r				
Reset	-	-	-	-	-	-						-				

Toggle Switch Register Address: 0x4022

# ENDPI0\_CONTROL

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-	-	-	-	-	-	-	STALL	FULL
Mode	r0	rO	r0	rO	r0	r0	w	r								
Reset	-	-	-	-	-	-	-	-	-	-	-	-	-	-	0	0

Endpoint In 0 Control Register Address: 0x5000

### ENDPI0\_DATA

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-				DA	ATA .			
Mode	r0	rO	r0	r0	rO	r0	r0	rO				,	v			
Reset	-	-	-	-	-	-	-	-					-			

Endpoint In 0 Data Register Address: 0x5002

# ENDPI1\_CONTROL

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-	-	-	-	-	-	-	STALL	FULL
Mode	r0	r0	rO	r0	r0	r0	r0	rO	r0	r0	r0	r0	rO	r0	w	r
Reset	-	-	-	-	-	-	-	-	-	-	-	-	-	-	0	0

Endpoint In 1 Control Register 0x5004

# ENDPI1\_DATA

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-				DA	ATA .			
Mode	r0	rO	r0	r0	rO	r0	r0	rO				,	v			
Reset	-	-	-	-	-	-	-	-					-			

Endpoint In 1 Data Register 0x5006

# ENDPO0\_CONTROL

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-	-	-	-	-	-	-	RDREQ	EMPTY
Mode	r0	rO	r0	rO	rO	rO	rO	r0	w	r						
Reset	-	-	-	-	-	-	-	-	-	-	-	-	-	-	0	0

Endpoint Out 0 Control Register Address: 0x5040

# ENDPO0\_DATA

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0		
Name	-	-	-	-	-	-	-	-	DATA									
Mode	r0	r0	rO	r0	rO	r0	rO	rO	r									
Reset	-	-	-	-	-	-	-	-	-									

Endpoint Out 0 Data Register Address: 0x5042