Registermap

LEDG

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-				LE	DG			
Mode	r0	r0	rO	r0	r0	r0	r0	rO				\	v			
Reset	-	-	-	-	-	-	-	-				0x	00			

LED Green Register Address: 0x4000

LEDR

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-					LE	DR				
Mode	r0	r0	r0	r0	r0	r0					١	v				
Reset	-	-	-	-	-	-					0x0	000				

LED Red Register Address: 0x4002

HEX0

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-	-				HEX0			
Mode	r0				w											
Reset	-	-	-	-	-	-	-	-	-				0x7f			

Seven Segment Digit 0 Register Address: 0x4010

HEX1

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-	-				HEX1			
Mode	rO	rO	r0	rO	rO	r0	rO	rO	rO				w			
Reset	-	-	-	-	-	-	-	-	-				0x7f			

Seven Segment Digit 1 Register

Address: 0x4012

HEX2

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-	-				HEX2			
Mode	r0	rO	r0	rO	rO	rO	r0	rO	r0				w			
Reset	-	-	-	-	-	-	-	-	-				0x7f			

Seven Segment Digit 2 Register

Address: 0x4014

HEX3

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-	-				HEX2			
Mode	r0	r0	r0	r0	rO	r0	r0	r0	r0				w			
Reset	-	-	-	-	-	-	-	-	-				0x7f			

Seven Segment Digit 3 Register

Address: 0x4016

KEY

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-	-	-	-	-		KE	ΞΥ	
Mode	r0	r														
Reset	-	-	-	-	-	-	-	-	-	-	-	-				

Pushbuttons Register Address: 0x4020

SW

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-					S	W				
Mode	r0	rO	r0	r0	r0	r0					ı	r				
Reset	-	-	-	-	-	-						-				

Toggle Switch Register Address: 0x4022

ENDPI0_CONTROL

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-	-	-	-	-	-	ZLP	STALL	FULL
Mode	r0	r0	rO	r0	rO	rO	r0	rO	r0	r0	r0	r0	rO	w	w	r
Reset	-	-	-	-	-	-	-	-	-	-	-	-	-	0	0	0

Endpoint In 0 Control Register Address: 0x5000

ENDPI0_DATA

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-				DA	ATA .			
Mode	r0	rO	r0	r0	rO	r0	r0	rO				,	v			
Reset	-	-	-	-	-	-	-	-					-			

Endpoint In 0 Data Register Address: 0x5002

ENDPI1_CONTROL

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-	-	-	-	-	-	ZLP	STALL	FULL
Mode	r0	r0	rO	r0	r0	r0	r0	rO	r0	r0	r0	r0	rO	w	w	r
Reset	-	-	-	-	-	-	-	-	-	-	-	-	-	0	0	0

Endpoint In 1 Control Register 0x5004

ENDPI1_DATA

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-				DA	ATA .			
Mode	r0	rO	r0	r0	rO	r0	r0	rO				,	v			
Reset	-	-	-	-	-	-	-	-					-			

Endpoint In 1 Data Register 0x5006

ENDPO0_CONTROL

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
Name	-	-	-	-	-	-	-	-	-	-	-	-	-	-	RDREQ	EMPTY
Mode	r0	rO	r0	rO	rO	rO	rO	r0	w	r						
Reset	-	-	-	-	-	-	-	-	-	-	-	-	-	-	0	0

Endpoint Out 0 Control Register Address: 0x5040

ENDPO0_DATA

Bit	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0		
Name	-	-	-	-	-	-	-	-	DATA									
Mode	r0	r0	rO	r0	rO	r0	rO	rO	r									
Reset	-	-	-	-	-	-	-	-	-									

Endpoint Out 0 Data Register Address: 0x5042